

How to set up a Tilos named user license

Note: Please install the software on the Terminal server with administrative privileges. Take the default installation folder or make an own selection. **There will be no common libraries (dll) installed or registered in the Windows environment.**

To learn which files are installed, please refer to the separate document *“Tilos 7 - Installation, program- and data folders.pdf”*

1. Preparation

Before starting the licensing process there have to be created 2 folders:

1. One is containing the Tilos license files:
All TS-Users need to have permission modify in this folder
2. One is containing the TilosUser.dat which controls and contains the named users:
All TS-Users need to have permission read in this folder. TilosUser.dat is a simple Text file which can be edited with common Editor, e.g Windows notepad.

The TilosUser.dat can also be located in the license folder. This is the default setting. If you wish to have no write access permission on the TilosUser.dat for normal Tilos users, we recommend to use a separate folder (see 2).

2. Licensing

The Licensing is working exactly as the licensing for the network (floating) license. Please refer to *“Tilos 7 licensing – general overview for users and administrators.pdf”*.

We recommend to use an UNC path for locating the license folder during the activation process. This allows the access from other client or server installations to this license folder.

In case of running TilosUser.dat in a separate folder: After licensing you have to edit Tilos.dat in the license folder. Add the line `TILOSUserPath=\\Servername\Licenses\Tilos7\` and change the UNC-Path to your location of TilosUser.dat

3. Configuring the TilosUser.dat

The TilosUser.dat is a simple table in text file in the format:

UserName	From	To	Comment
ba	2000-01-01	2010-12-31	User Thorsten Balthasar
us123-ab	2010-05-01	2010-07-31	User us123 during his residence in headquarter office

Description:

The username has to be identic with the Windows user name. Each User name on the list is allowed to access Tilos. Users not on the list will not have access to Tilos.

The fields From/To define the time range that this user has access to Tilos. Format: YYYY-MM-DD

An Administrator has to maintain this text file due to the defined user accesses.